

# Readme

Hi,

Thanks for purchasing Typography 4 Photoshop Action.

**Please watch the video below for demonstration of how to use and customize the look of your action to get the most out of the effect:**

<https://youtu.be/bp7kVnqA-Kc>

**Before you play the action check the following:**

1. Your photo is in "**RGB**" color mode
2. Your photo is in "**8bit**" color mode
3. Make sure that your image is "**Background**" layer, if it is not, just go to **Layer -> New -> Background from Layer**.
4. You are running the English version of Photoshop.
5. If you are using another language, watch the video below to see how you can change it to English:

<http://www.youtube.com/watch?v=GJAiu5W2gLE>

**After you play the action, you can change it back to your native language.**

6. Please don't use small resolution images. For best results use photos that are between 2000px - 3500px high/wide.

**How to install the action:**

1. Start Photoshop, go to the "**Window**" menu and select "**Actions**". A window will now appear to the right hand side.
2. Inside the "**Actions**" window, click on the top right hand corner icon to reveal the drop down menu and from there select "**Load Actions...**". Select the action which came with the download and click "**Load**".
3. The action will now appear in the actions panel.

# Readme

## How to use the action:

1. Go to **File** -> **Open**, choose your photo and click "**Open**" to open a photo to work with.
2. Go to **Layer** -> **New** -> **Layer...** to create new layer, and name it "**brush**" (**Important: all letters must be lower case**).
3. With the "**brush**" layer selected, fill in your subject with a color.
4. Now open the "**Typography 4**" action folder, choose the action according to letter size and direction that you want and click on "**Play button**".

## \*Important:

If you are using **Photoshop CC** version, copy the "**Random Fill.jsx**" file that came with download and paste it to:

Windows 32 bit: Program Files (x86) -> Adobe -> Adobe Photoshop CC -> Presets -> Deco

Windows 64 bit: Program Files -> Adobe -> Adobe Photoshop CC (64 Bit) -> Presets -> Deco

Mac: Applications -> Adobe Photoshop CC -> Presets -> Deco

You can create "**Backup**" of your "**Random Fill**" file by copying it to some location before you replace it. After you play the action, you can replace the new "**Random Fill**" file with previous.

Again please watch the above video tutorial for a demonstration of these steps.

Take a look at my other actions if you are interested:

<http://graphicriver.net/user/unicdesign/portfolio>

If you need any help with the action or you got any questions please contact me via my Envato profile page.

Thank You for your support,

UnicDesign